




# PHIL TECHNOLOGIES PRIVATE LIMITED




**Release Notes For MFS110  
RD Service - Windows  
Version 1.0.4  
10-July-2024**

	PHIL TECHNOLOGIES PRIVATE LIMITED	
	Product Release Notes (MFS110 RD Service - Windows)	10.07.2024

Table of Contents

Table of Contents	1
1. Introduction	2
2. About This Release	2
3. Compatible Products	2
4. Upgrades	3
5. New Features	5
6. Known Bugs and Limitations	5
6.1 General Note	5
6.2 Defect or Bug	5

 <b>Radium</b>	PHIL TECHNOLOGIES PRIVATE LIMITED	
	Product Release Notes (MFS110 RD Service - Windows)	10.07.2024

## 1. Introduction

MFS110 RD Service facility to capture biometric data of user/resident that will be used for Authentication/EKYC using Aadhaar authentication/EKYC API.

## 2. About This Release

Features added in this release as below.

Functional Improvement.

## 3. Compatible Products

This product has been tested on the following platforms and below MFS100 Driver Setup.

### Platform Supports


- 1) Windows 10 (64 bit & 32 bit)
- 2) Windows 11 (64 bit)

### Prerequisites

- 1) MFS110 Driver Setup 1.1.0.0

Note: MFS110 Driver setup will install below setups as prerequisites.

- A) VC++ 2013 Redist (x86)
- B) VC++ 2015-2019 Redist (x86) or VC++ 2015-2022 Redist (x86)
- C) Dot Net Framework 4.8 or higher

 <b>Radium</b>	PHIL TECHNOLOGIES PRIVATE LIMITED	
	Product Release Notes (MFS110 RD Service - Windows)	10.07 .20 24

## 4. Upgrades

### 4.1 RD Service Upgrade

There are two processes to upgrade MFS110 RD Service Version 1.0.3 to 1.0.4.

#### 1) Manual RD Service Upgrade Process

You can download MFS110 RD service setup version 1.0.4 & MFS110 Driver Setup (If not installed) Version 1.1.0.0 from below download Portal <https://www.radiumbox.com/download>

**If driver setup not installed, then download using below LINK.**  
<https://www.radiumbox.com/download>

#### 2) Auto RD Service upgrades process from Management Server


Management Server will have facility to upgrade MFS110 RD Service 1.0.3 to 1.0.4 remotely over the air.

One very restart, RD Service will check latest version available on Management Server, and Management Server will provide upgraded packages to RD Service.

### 4.2 Firmware Verification

After “Framework is ready to use” popup, RD Service will ask for firmware verification as below.



 <b>Radium</b>	PHIL TECHNOLOGIES PRIVATE LIMITED	
	Product Release Notes (MFS110 RD Service - Windows)	10.07 .20 24


Click on “OK” to verify firmware. After that please wait for a while and do not disconnect the device and wait for next message.



Once firmware verified, below popup will be displayed. Device will be restarted and wait for Device attached message and after that “Framework is ready to use” popup will be displayed. And now service is ready to use.



 <b>Radium</b>	PHIL TECHNOLOGIES PRIVATE LIMITED	
	Product Release Notes (MFS110 RD Service - Windows)	10.07.2024



## 5. New Features

Features added in this release as  
below. Functional Improvement.

## 6. Known Bugs and Limitations

### 6.1 General Note

MFS110RD service setup version 1.0.4 having dependency of Dot Net Framework 4.8 or higher, VC++ 2013 redistributable and VC++ 2015-2019 or VC++ 2015-2012 redistributable, so its recommendation to Install MFS110 Driver Setup 1.1.0.0 or higher.

### 6.2 Defect or Bug

NA